

**KONFIGURACJA DIALER-a
SIP NET2PHONE**


1. Ściągnij plik instalacyjny, rozpakuj i zainstaluj na komputerze.
2. Wpisz konto i pin:



The image shows a Net2Phone login dialog box. At the top is the Net2Phone logo. Below it, the text reads "Please enter your account number and PIN." There are two input fields: "Account Number:" with the value "1234567890" and "PIN:" with four dots. Below the fields are two checked checkboxes: "Save my account number and PIN" and "Sign in automatically when Net2Phone Dialer starts". At the bottom are four buttons: "Settings...", "Help", "OK", and "Exit".

3. Wybierz Settings.... i wprowadź zgodnie z rysunkiem.

Jako Secondary SIP Proxy należy wpisać: **ippbx.net2phone.com**.



The image shows the "Settings" dialog box for Net2Phone. The "Network" tab is selected in the left sidebar. The "SIP Proxies" section has "Primary SIP Proxy" set to "sip.net2phone.com" with "Disable Primary" checked, and "Secondary SIP Proxy" set to "ippbx.net2phone.com". "SIP Proxy Port" is "5060" with "Automatically Assign Port" checked. There is an unchecked "Receive *72 Calls" checkbox. The "Local Ports" section has "Use Automatic Port Assignment" checked. "Control UDP Port Range" and "Voice UDP Port Range" are both set to "0-0" with explanatory text. The "Bandwidth" section has "Connection Type" set to "E1/T1/LAN - High - 1.5M and up". "OK" and "Cancel" buttons are at the bottom right.

4. Zatwierdź zmiany.
5. Podłącz słuchawki i mikrofon lub inne urządzenia multimedialne zapewniające komunikację głosową.
6. Wybieranie numeru.

Pierwsze okienko musi być puste.

W drugim należy wpisywać numer jak w TP SA –

nr krajowy 0_kod-miasta_numer

nr zagraniczny 00_kod-państwa_numer.



7. Zarządzanie kontem.

Na stronie www.myaccountcenter.net znajduje się biling oraz różne opcje, które można ustawiać zgodnie z własnymi wymaganiami i potrzebami.